

FLAIRFORM Dosage Chart

This dosage chart is designed for hydroponics (hydro), coconut fibre (coco) or soil gardening. Simply select which phase of plant growth your plants are in (see PLANT PHASE) then add the specified nutrient and additives to the reservoir. Dose rates are expressed in ml per litre.

(1 tsp = 5ml | 1 Qt = 946ml | 1 US Gal = 3.785 litres)

Plant Phase	Nutrient (ml per litre)	Additives (ml per litre)						
		TWINTECH Plus	GROSTORM	CMX	STOPBLOC	BUDSTORM	PYTHOFF (10g/L)	SILIKAMAJIC
Cuttings & Seedlings	TWINTECH FERTILIZER: 5ml (Hydro/Coco/Soil)	5ml	-	-	-	-	-	-
Vegetative (Grow) Commence once roots and foliage are growing strongly	Select ONE of the following FLAIRFORM nutrients: a) GREENDREAM-1 GROW: Hydro: 5.5ml Coco: 4ml Soil: 4ml b) GREENDREAM-2 GROW A & B: Hydro: 3ml Coco: 2.2ml Soil: 2.2ml c) ORGANABUD: 2ml (For soil only) d) DUTCHTREAT GROW: Hydro: 5ml Coco: 4.2ml Soil: 4.5ml	-	Hydro: 0.5ml Coco: 0.5ml Soil: 1ml	Hydro: - Coco: 0.5ml Soil: 1ml	0.2ml	-	Hydro: 0.2ml Coco: 0.2ml Soil: - (every 4 days)	Hydro: 0.2ml Coco: 0.1ml Soil: 0.1ml
Bloom - Stage 1 Commence when floral buds appear	Select ONE of the following FLAIRFORM nutrients: a) GREENDREAM-1 BLOOM: Hydro: 6ml Coco: 4ml Soil: 4.5ml b) GREENDREAM-2 BLOOM A & B: Hydro: 3.3ml Coco: 2.2ml Soil: 2.5ml c) ORGANABUD: 2.7ml (For soil only) d) DUTCHTREAT BLOOM: Hydro: 6ml Coco: 5.5ml Soil: 5.5ml	-	Hydro: 0.5ml Coco: 0.5ml Soil: 1ml	Hydro: - Coco: 1ml Soil: 1ml	0.2ml	-	Hydro: 0.2ml Coco: 0.2ml Soil: - (every 4 days)	Hydro: 0.2ml Coco: 0.1ml Soil: 0.1ml
Bloom - Stage 2 Commence once small fruits appear	Select ONE of the following FLAIRFORM nutrients: a) GREENDREAM-1 BLOOM: Hydro: 5.5ml Coco: 3.5ml Soil: 4ml b) GREENDREAM-2 BLOOM A & B: Hydro: 3ml Coco: 2ml Soil: 2.2ml c) ORGANABUD: 2.5ml (For soil only) d) DUTCHTREAT BLOOM: Hydro: 5.5ml Coco: 5ml Soil: 5ml	-	Hydro: 0.5ml Coco: 0.5ml Soil: 1ml	Hydro: - Coco: 1ml Soil: 1ml	0.2ml	1ml	Hydro: 0.2ml Coco: 0.2ml Soil: - (every 4 days)	Hydro: 0.2ml Coco: 0.1ml Soil: 0.1ml
Bloom - Stage 3 7-14 days prior to harvest	Select ONE of the following FLAIRFORM nutrients: a) GREENDREAM-1 BLOOM: Hydro: 2ml Coco: 2ml Soil: 2ml b) GREENDREAM-2 BLOOM A & B: Hydro: 1ml Coco: 1ml Soil: 1ml c) ORGANABUD: 1ml (For soil only) d) DUTCHTREAT BLOOM: Hydro: 2ml Coco: 2ml Soil: 2ml	-	Hydro: 0.5ml Coco: 0.5ml Soil: 1ml	Hydro: - Coco: - Soil: 0.5ml	0.2ml	-	Hydro: 0.2ml Coco: 0.2ml Soil: - (every 4 days)	Hydro: 0.2ml Coco: 0.1ml Soil: 0.1ml

See Flairform Dosage Calculator for further details (www.flairform.com/dosage.htm)

NOTES

Dosing procedure:

Step 1. Fill the nutrient reservoir with water then add nutrient and additives: Add in the sequences shown in the chart (from left to right). PYTHOFF and SILIKAMAJIC must be pre-diluted into ~1 litre (1 Qt) of plain water before being added to the reservoir.

Step 2. Immediately check pH using the pH TEST KIT (Disregard if using ORGANABUD): Maintain pH between 5.0 and 6.5. Adjust using pH UP or DOWN.

Step 3. Feed frequency and volume:

- Hydroponics; Coco: Use this nutrient solution with each watering.
- Soil: Use this nutrient solution every second watering. Halve these dose rates if the nutrient solution is being used with each watering.

Further information: http://www.flairform.com/hints/feed_frequency_volume.htm

Step 4. Maintain nutrient concentration (For 'recirculating' hydroponic systems only): Keep the reservoir topped up with water. Monitor nutrient strength using a conductivity (EC) meter. Do not allow EC to fall more than ~20% below the target EC. Maintain EC by adding nutrient..

Foliar feeding: For improved growth results, mist plants every 7-14 days using the following treatments:

- TOPFERT (5-10ml/L) mixed with TOPWET (1-2ml/L). See label rates for seedlings/cuttings.
- SILIKAMAJIC (3ml/L) mixed with TOPWET (1-2ml/L).

Spray ~1 hour prior to the start of daylight (or "lights-on") and use low salinity/soft water.

Discarding & flushing: For recirculating systems ensure to discard, flush and replace nutrient every 7-14 days (do every 7 days if using hard/salty water). For run-to-waste systems (especially soil & coco), flush medium at least every 7 days.

www.flairform.com | sales@flairform.com | T/F +61 8-9314-7595

Distribution: Australia 8-9314-7595 | Americas 215-395-6353 | UK 1925-822-503 | Europe (+61) 8-9314-7595